






-  *Save algorithm files*   : if checked, the *Algorithm raster* (page 142) is saved, in addition to the classification raster, in the same directory as the *Classification output*; a raster for each spectral signature used as input (with the suffix `_sig_MC ID_C ID`) and a general algorithm raster (with the suffix `_alg_raster`) are created;
- *BATCH*  : add this function to the *Batch* (page 102);
- *RUN*  : choose the output destination and start the image classification;

## Clustering

- *Clustering of band set* (page 75)
- *Seed signatures* (page 76)















Fig. 39:  Clustering

This tab allows for the *Clustering* (page 148) of a *Band set* (page 31). In particular, *K-means* (page 148) and *ISODATA* (page 148) methods are available.









A report .txt is saved along with the classification, containing the class spectral signature and the spectral distance thereof.

### Clustering of band set

- *Select input band set* : select the input *Band set* (page 31);
- *Method*  *K-means*  *ISODATA*: select the clustering method *K-means* (page 148) or *ISODATA* (page 148);

-  *Distance threshold* : if checked, for K-means: iteration is terminated if distance is lower than threshold; for ISODATA: signatures are merged if distance is greater than threshold;
- *Number of classes* : number of desired output classes;
- *Max number of iterations* : maximum number of iterations if *Distance threshold* is not reached;
- *ISODATA max standard deviation* : maximum standard deviation considered for splitting a class, for ISODATA algorithm only;
- *ISODATA minimum class size in pixels* : desired minimum class size in pixels, for ISODATA algorithm only;
-  *Use value as NoData* : if checked, set the value of NoData pixels, ignored during the calculation;

## Seed signatures

-  *Seed signatures from band values*  *Use Signature list as seed signatures*  *Use random seed signatures*: select one options for seed signatures that start the iteration; the option *Seed signatures from band values* divides the spectral space of the *Band set* (page 31) to get spectral signatures; the option *Use Signature list as seed signatures* uses the spectral signatures checked in *ROI & Signature list* (page 24); the option *Use random seed signatures* randomly selects the spectral signatures of pixels in the *Band set* (page 31);
- *Distance algorithm*  *Minimum Distance*  *Spectral Angle Mapping*: select *Minimum Distance* (page 137) or \* *Spectral Angle Mapping* (page 139) for spectral distance calculation;
-  *Save resulting signatures to Signature list*: if checked, save the resulting spectral signatures in the *ROI & Signature list* (page 24);
- *BATCH* : add this function to the *Batch* (page 102);
- *RUN* : choose the output destination and start the calculation;




## PCA

- *Principal Component Analysis of Band set* (page 76)

This tab allows for the PCA (*Principal Component Analysis* (page 146)) of bands loaded in the *Band set*.

A report .txt is saved along with the PCA bands, containing the covariance matrix, correlation matrix, eigen vectors, and eigen values.

## Principal Component Analysis of Band set

- *Select input band set* : select the input *Band set* (page 31);
-  *Number of components* : if checked, set the number of calculated components; if unchecked, all the components are calculated;